

POCKET PC (PPC) SETUP

To use Meditrek on your Pocket PC (PPC for short), first you need to connect your PPC to the internet. Then you need to download and install SuperWaba, then Meditrek itself. After you enter your case logs on your PPC, you will be able to upload the data directly to the web server.

Full instructions for connecting your PPC to the internet are beyond the scope of this document; please read the documentation that came with your device, and/or contact the manufacturer's technical support. We will note merely that there are three possibilities for connecting your PPC to the internet: (1) Wireless network; (2) "Pass-through" connection via a host PC with internet access (please read your PPC's ActiveSync documentation); or (3) as part of a cell-phone/PDA combo, using the cell phone's internet connection.

- [Installing SuperWaba](#) (Initial setup only)
 - [Installing Meditrek](#) (Initial setup or upgrade)
 - - Third year students ONLY: [Installing a new schedule](#)
 - [Uploading your logs](#)
 - [Removing and Reinstalling](#) (Troubleshooting)
-

A. Installing SuperWaba

SuperWaba is a portable subset of Java that has been optimized for use on devices with small screens. This is required to enable your PPC to run Meditrek. You have to install it on your PPC during the **INITIAL SETUP ONLY**. Please follow the steps listed below. **All web related steps refer to your PPC.**

1. Connect your PPC to the internet, then start Internet Explorer on your PPC.
 2. Go to <https://www.meditrek.com/njms/pda.htm> (please note, it is https)
 3. On the top of the page, above the Meditrek Logo, select one of the **SuperWaba PocketPC** files, according to the processor type of your PPC. Most PPCs, including Dell Axim and Compaq iPAQ, use the **ARM** processor. ([Here's a list](#) of PPCs built on ARM type processors.) When you click the file, it will install automatically on your PPC. During installation a new 'SuperWaba' folder will be created on your PPC, and under Programs the Superwaba icon will be displayed, called 'SuperWaba VM'.
-

B. Installing MEDITREK

These steps should be repeated each time you **UPGRADE MEDITREK**, or when you install a new **SCHEDULE** (third year medical students ONLY). If you just installed SuperWaba, please jump directly to step 4. If you are installing a new schedule, please skip step 4. **All web related steps refer to your PPC.**

1. Connect your PPC to the internet, then start Internet Explorer on your PPC.
 2. Go to <https://www.meditrek.com/njms/pda.htm> (please note, it is https)
 3. Login using your Meditrek User Name and Password.
 4. Select from the list one of the **MeditrekInstall...CAB** files, according to the processor type of your PPC, and your grade level. When you tap on the CAB file, it will install automatically on your PPC. During installation a new 'Meditrek' folder will be created under the 'SuperWaba' folder, and under Programs the Meditrek icon will be displayed.
 5. Third year medical students ONLY - Install the schedule by clicking on **MeditrekScheduleInstall.cab (date)**.
-

C. Uploading your logs

Your web-enabled PPC and Meditrek (Version 2.8 and above) allow you to upload your logs to the

web server directly from your PPC. To initiate the upload please follow the steps listed below. These steps should be repeated each time you **UPLOAD YOUR LOGS**. **All web related steps refer to your PPC.**

1. Connect your PPC to the internet.
2. Start Meditrek, and tap the 'Meditrek v2.8' label on the top of the screen.
3. Select 'Manage records...' from the list.
4. Check if the records on the display are correct.
5. Click the 'Upload All to Web' button, and watch the messages.

You can also manage (view & edit) your uploaded records via Meditrek through a regular web browser running on a laptop or desktop PC.

D. Removing & Reinstalling

If for any reason you need to reinstall Meditrek, follow these steps.

1. Go to Start | Settings | System | Remove Programs, highlight and remove Meditrek first, then SuperWaba.
2. Go to Start | File Explorer, and from under My Device delete the SuperWaba folder.
3. If your data file on your PPC contains good records, you should establish the link between your PPC and host PC, and using Windows Explorer of your host PC, copy Mobile Device/My Pocket PC/My Documents/MediTrekData.dat over to your host PC, then send it via email to our address, support@HSoft.org. If you have no records to save, or you saved them already, on your PPC go to My Device/My Documents and delete MediTrekData.dat.
4. Proceed with the installation of SuperWaba and Meditrek as described at the top of this page, Sections A and B.